

## Dimdim VMWare Appliance:

Dimdim VMWare Appliance is a VMWare based Dimdim Virtual Image containing all the required Dimdim Components. Dimdim VMWare Appliance can be run on any operating system

If you need to read more about VMWare please follow the below link.

<http://www.vmware.com/solutions/whit...alization.html>

### Pre-requisite

Below are pre-requisites for running the Dimdim VMWare Image.

- 1) You need to download VMWare Player to run the Dimdim VM Image <http://www.vmware.com/products/player/>
- 2) In order to run the Dimdim VMWare Image you would need to be either on a DHCP Network so the Dimdim VMWare Image can acquire an IP Address or you need to have a public static IP Address which can be assigned to the Dimdim VMWare Image.
- 3) The Dimdim VMWare Image to be downloaded is around 2GB size, you would need to download this image on the machine where you intend to run this Dimdim VMWare Image.

Please follow the below steps to get your Dimdim VMWare Image up.

1. unzip VMWare image.
2. `chmod +x *` (In case you are on linux)
3. Import the VMWare image to the VMWare Player.
3. Start the VMWare image from the player.
4. Please make sure your VMWare Network Settings is in Bridged mode.
5. User credentials for Dimdim Virtual machine is as follows

Username : root

Password : dimdim

### Automatic Network Setup:

If your network is a DHCP Enabled Network the Dimdim VMWare Image would automatically be assigned an IP Address at the time of loading, once the VMWare Image is loaded please login to the VMImage and follow the below steps.

- After the VMWare image is booted, the startup scrip will configure the required details to run all the Dimdim Components and Start the Dimdim components automatically.

- You can know the IP Address of the VMWare Image by typing ifconfig from the terminal.

Example:

```
root@localhost dimdim]# ifconfig eth0
```

The output will look like:

```
eth0  Link encap:Ethernet HWaddr 00:0C:29:CA:FA:7C
      inet addr:192.168.1.10 Bcast:125.255.255.255 Mask:255.0.0.0
```

The IP address for the above example is 192.168.1.10

### Manual Network Setup:

If the Dimdim VMWare Image do not get the IP address automatically then you need to assign an IP Address to the Dimdim VMWare Image:

Please follow the below steps to assign a static IP Address to your VMWare Image:

#### 1. Specify IP Address in ifcfg-eth0 file

- Open the file by typing the below command from a terminal

```
root@localhost dimdim]#vi /etc/sysconfig/network-scripts/ifcfg-eth0
```

- Modify the below parameters in the file.

```
DEVICE=eth0
BOOTPROTO=static
BROADCAST=XXX.XXX.XXX.255
IPADDR=XXX.XXX.XXX.XXX
NETMASK=255.255.255.0
NETWORK=XXX.XXX.XXX.0
ONBOOT=yes
```

Please note that the hardware address should remain the same as it is for the vmware image.

#### 2. Specify Name Server IP Address in resolv.conf

- Open the file by typing the below command from a terminal

```
root@localhost dimdim]#vi /etc/resolv.conf
```

- Modify the below parameters in the file.

```
nameserver XXX.XXX.XXX.XXX
nameserver XXX.XXX.XXX.XXX
```

3. vi /etc/sysconfig/network

```
NETWORKING=yes
NETWORKING_IPV6=yes
HOSTNAME=localhost.localdomain
GATEWAY=XXX.XXX.XXX.1
```

4. Restart the Network Service.

- Type the below command to restart the network service.

```
root@localhost dimdim]#service network restart
```

5. Confirm IP Address of your VMWare Image

- Type the below command to check IP Address of your VMWare Image

```
root@localhost dimdim]#ifconfig eth0
```

Please ensure that you have provided the proper netmask / broadcast ip address / default gateway/ dns server address.

Dimdim VM appliane Directory Structure:

Once you have mounted the vm image you will get the following directory structure :

```
/usr/local/
```

```
|
|--dimdim
|
|--CobrowsingManager
|
|--DTP3
|
|--nginx
|
|--ConferenceServer
|
|--red5
|
```

```

|--ThirdPartyPackages
|
|--Mediaserver
|
|--mailbox

```

Also you will find some files namely:

```

StopDimdim.sh
StartDimdim.sh
Config-ipaddress.pl

```

## Dimdim all component IP Configuration

There may be two cases:

1. Network has public and private IP mapping,

ExternalIP:port --> Internal:port

Please note that port should be same, Port 80 is recommended.

For example: 123.X.X.X:80 ---> 192.168.X.X:80

publicIP is mapped to privateIP

Use Config-ipaddress.pl like below

```

cd /usr/local/dimdim
./Config-ipaddress.pl 123.X.X.X 80 192.168.X.X

```

2. VM has a singleIP, There is no network mapping(no Network Address Translation):

Use Config-ipaddress.pl like below

```

cd /usr/local/dimdim
./Config-ipaddress.pl 123.X.X.X 80

```

Start Dimdim Components:

```

cd /usr/local/dimdim
./StartDimdim.sh

```

Stop Dimdim Components:

```

#cd /usr/local/dimdim
./StopDimdim.sh

```

Once Done the above steps you can start meeting from your browser.

URL to start meeting from Dimdim Web Meeting Server:

<http://<ip of vm>/dimdim/>

When VM get start, Dimdim services will start automatically,

\*If they don't start automatically do the following steps:

Go to

```
cd /usr/local/dimdim
```

```
./StartDimdim.sh
```

It will start all the Dimdim components

To stop all Dimdim components please use

```
./StopDimdim.sh
```