

??

???? Incoming Calls ????????????? sip.conf ?? call-limit=xx ?????????????

1. ?????? call-limit ?????????????
2. ?????? call-limit ?????? SIP ??? 480????? 503 ?????? chan_sip.c ?????????? asterisk?
3. ?? call-limit ?????? chan_sip.c ?????????????????????

? DP ??? call-limit ????

????

?? /etc/asterisk/extensions_custom.conf

; Below is used to limit the maximum number of incoming calls for trunk ccnet

```

;
[my-from-trunk-call_limit-ccnet]
exten => _,1,Set(DIAL_TRUNK=2) ;2 is trunk# for ccnet, you can get it on FreePBX
exten => _,n,Set(GROUP()=OUT_${DIAL_TRUNK})
exten => _,n,Noop(Calls usage(activated): ${GROUP_COUNT(OUT_${DIAL_TRUNK}))})
exten => _,n,GotoIf(["${OUTMAXCHANS_${DIAL_TRUNK}}foo" = "foo"]?nomax)
exten => _,n,GotoIf(["${GROUP_COUNT(OUT_${DIAL_TRUNK})} > ${OUTMAXCHANS_${DIAL_TRUNK}}
]?chanfull)
exten => _,n(nomax),Noop(Passing the call to from-trunk)
exten => _,n,Goto(from-trunk,${EXTEN},1)
exten => _,n(chanfull),Noop(max channels used up)
exten => _,n,Hangup(42) ;42 is causecode, which will return 503 response code
exten => h,1,Hangup

```

????

- [Asterisk Hangupcase](#)
- [Hangup Cause Code](#)