



????,?? RHEL ?????????? Guest ? console ??????????,????!???? Guest ? /var/log/message ????? console ???  
 ?.???????????? security ?????? console ?!????????? root ??? Guest ? console ??? ?????? Guest ?????????? xm  
 console ??????????!!

1. ? /boot/grub/grub.conf  
 ?? console ? "console=tty0 console=xvc0"

```
[root@benjr ~]# vi /boot/grub/grub.conf
title Red Hat Enterprise Linux ES (2.6.9-78.ELxenU)
root (hd0,0)
kernel /boot/vmlinuz-2.6.9-78.ELxenU ro root=LABEL=/ console=tty0 console=xvc0
initrd /boot/initrd-2.6.9-78.ELxenU.img
```

2. /etc/inittab ?????????? comport ?????, ?????????? /etc/inittab,

```
[root@benjr ~]# vi /etc/inittab
co:2345:respawn:/sbin/agetty xvc0 9600 vt100-nav
```

3. /etc/securetty ?? PAM ?????? root ?????? comport ???? ,????????? /etc/securetty:

```
[root@benjr ~]# vi /etc/securetty
xvc0
[root@benjr ~]# xm list
```

Name	ID	Mem(MiB)	VCPUs	State	Time(s)
Domain-0	0	1231	4	r-----	150.1
rhel4.6	2	255	1	-b----	0.1
rhel5	4	511	1	-b----	2.2

???????????? running ??? Guest.

```
[root@benjr ~]# xm console rhel4.6
```

????????????????? console ?????!

????????? : <http://benjr.tw/?q=node/374>