

??????,?? RHEL ?????????? Guest ? console ??????????,????!?!???? Guest ? /var/log/message ???? console ???
 ?????????????? security ?????? console ??!????????? root ??? Guest ? console ???????? Guest ?????????? xm
 console ??????????!!

1. ? /boot/grub/grub.conf
 ?? console ? "console=tty0 console=xvc0"

```
[root@benjr ~]# vi /boot/grub/grub.conf
title Red Hat Enterprise Linux ES (2.6.9-78.ELxenU)
root (hd0,0)
kernel /boot/vmlinuz-2.6.9-78.ELxenU ro root=LABEL=/ console=tty0 console=xvc0
initrd /boot/initrd-2.6.9-78.ELxenU.img
```

2. ./etc/inittab ????????? comport ????? ,??????? /etc/inittab,

```
[root@benjr ~]# vi /etc/inittab
co:2345:respawn:/sbin/agetty xvc0 9600 vt100-nav
```

3. ./etc/securetty ?? PAM ????? root ??? comport ????? ,????????? /etc/securetty:

```
[root@benjr ~]# vi /etc/securetty
xvc0
[root@benjr ~]# xm list
Name ID Mem(MiB) VCPUs State Time(s)
Domain-0 0 1231 4 r---- 150.1
rhel4.6 2 255 1 -b--- 0.1
rhel5 4 511 1 -b--- 2.2
```

????????? running ??? Guest.

```
[root@benjr ~]# xm console rhel4.6
```

????????????? console ???!!

?????? : <http://benjr.tw/?q=node/374>