

Q):How to increase the numbers of trunk button in FOP(Flash Operator Panel)

A):1: Edit /var/lib/asterisk/bin/retrieve_op_conf_from_mysql.pl

simply adjust these lines like.
My sample as the following.

```
##### STYLE INFO #####
$extenpos="2-40";
$trunkpos="47-60,67-90";
$confepos="";
$queuepos="42-45,62-65";
```

(Trunk has 2 columns, and each column has 14 positions)

2: Edit /var/www/html/panel/op_buttons.cfg
this one adjusts the sizes, colors and fonts of buttons and panel rectangles.

If you want to customize the positions of each button and do not like the layout created by freepbx, you have to comment out the line "include => op_buttons_additional.cfg" in op_buttons.cfg and create a file op_buttons_custom.cfg.

My sample as the following

```
include => op_buttons_additional.cfg
```

```
; use this for your customizations to FOP
include => op_buttons_custom.cfg
```

```
[rectangle]
x=492
y=32
width=491
height=133
line_width=0
line_color=ff1010
fade_color1=ff1010
fade_color2=a01000
rnd_border=2
alpha=20
layer=bottom
```

```
[rectangle]
x=492
y=167
width=491
height=427
line_width=0
```

line_color=10ff10
fade_color1=10ff10
fade_color2=10ff00
rnd_border=2
alpha=20
layer=bottom

[rectangle]
x=-1
y=32
width=491
height=564
line_width=0
line_color=1010ff
fade_color1=1010ff
fade_color2=1010ff
rnd_border=2
alpha=10
layer=bottom

[LEGEND]
x=500
y=170
text=Trunks
font_size=18
font_family=Times New Roman
use_embed_fonts=1

[LEGEND]
x=500
y=32
text=Queues
font_size=18
font_family=Arial
use_embed_fonts=1

[LEGEND]
x=10
y=32
text=Extensions
font_size=18
font_family=Arial
use_embed_fonts=1