



??:

Windows ???? SMB (Session Message Block protocol, ??? NetBIOS ? LanManager protocol.) ,?????????????,? samba ?? Linux ???? SMB (NetBIOS) ??????????????.????? samba ?? Windows ? Linux ??????????????????. Windows ? Linux ?? SMB /NMB ??????:

???? SMB(NetBIOS)?!!????????????????.

NetBIOS

??? IBM ???? NetBIOS API(Network Basic Input/Output System Application Program Interface),?? NetBIOS ? 18 ? API ?,?????????????????. ?? NetBIOS ????(broadcasts)?????.?????????(routed).?????????????.NetBIOS ?? session layer protocol(?5?,???)

NetBEUI

?????NetBIOS???,NetBEUI(NetBIOS Extened User Interface),?????????????.NetBEUI ?? data-link layer protocol (?2?,?????).

SMB(NetBIOS)

Windows NT4.0 ??????(?????????),????(wins)...???? NetBIOS over NetBEUI?????.??? NetBIOS ??? over TCP/IP ? Windows 2000 ?????(?????????), Linux ? samba server or NETBIOS over IPX(Internetwork Packet Exchange) ? NT ?? NWLINK

note:

- 1.?????????????,?? Roter ?, Router ??????????.????????????? InterNet ?,???????
- 2.NetBEUI ?? data-link layer protocol (?2?,?????)

Samba ?????? <http://www.samba.org>

RHEL5 - Samba (?) ?? samba ???

???? samba ???,????? /Server ??????? samba ? rpm ???????? yum ???.

```
[root@benjr ~]# rpm -aq | grep samba
samba
samba-common
samba-client
system-config-samba
```

?? samba ? RedHat ??????? /Server ????????

```
[root@benjr ~]# rpm -ivh samba-common.rpm
[root@benjr ~]# rpm -ivh samba-client.rpm
[root@benjr ~]# rpm -ivh samba.rpm
[root@benjr ~]# rpm -ivh system-config-samba
```

?? samba ????????????

```
[root@benjr ~]# chkconfig smb on
[root@benjr ~]# chkconfig --list smb
smb    0:off 1:on 2:on 3:on 4:on 5:on 6:off
```

???? samba ??

```
[root@benjr ~]# service smb start
Starting SMB services:      [ OK ]
Starting NMB services:      [ OK ]
```

RHEL 5 ??? #**system-config-samba** ?????????????? samba ???,????????????????? samba ??? /etc/samba/smb.conf ,????????? samba ????.

```
[root@benjr ~]# cat /etc/samba/smb.conf
#===== Global Settings =====
[global]
workgroup = mygroup
server string = Samba Server Version %v
netbios name = benjr
security = user
passdb backend = tdbSAM
#===== Share Definitions=====
[homes]
comment = Home Directories
browseable = no
writeable = yes
```

```
; valid users = %S
; valid users = MYDOMAIN\%S

[printers]
comment = All Printers
path = /var/spool/samba
browseable = no
; guest ok = no
; writeable = no
printable = yes
```

???????????????

1.[global] ?????? samba ????

??? [global] ? security ??????????,samba 3.X ????????????

2.[share] ??????????????????

/etc/samba/ ?? ????

```
[root@benjr ~]# ll /etc/samba/
total 52
-rw-r--r-- 1 root root 20 Apr 3 2008 lmhosts
-rw----- 1 root root 4096 Apr 12 06:59 passdb.tdb
-rw----- 1 root root 8192 Apr 12 06:59 secrets.tdb
-rw-r--r-- 1 root root 10043 Apr 14 03:37 smb.conf
-rw-r--r-- 1 root root 97 Apr 3 2008 smbusers
```

1."/etc/samba/lmhosts" ?? NetBIOS name ? IP ????

2."/etc/samba/passdb.tdb" ?????? samba server ????????????

3."/etc/samba/secrets.tdb" ?? samba ????

4."/etc/samba/smb.conf" samba ????

5."/etc/samba/smbusers" UNIX name ? samb name ????

??? samba ?????????????? /etc/samba/smbpassword ,???????? samba server ?????????,?????????????????????

?:

1.??????,???????.

2.??? samba server ?????? smbpasswd ?,??? samba server ??????????.

3.smbpasswd ??????????????????????.

4.????????????????? samba server ????,

???? RHEL5 ???????????????,????????????? ?????? tdbsam(.tdb) ????? Samba ???????,??? LDAP ?????.

1.Plain Text: :

2.smbpasswd : Encrypted Password Database

3.tdbsam:

4.ldapsam:

5.MySQL:

6.XML:**RHEL5 - Samba (?) samba ??????**

RHEL 5 ????? #**system-config-samba** ??? samba ?????????????????????:
nmblookup : ?? NetBIOS ??? IP addresses

```
[root@benjr ~]# nmblookup benjr
querying benjr on 192.8.1.255
192.8.1.85 benjr<00>
```

smbstatus : ?? samba server ????????????

```
[root@benjr ~]# smbstatus
Samba version 3.0.28-0.el5.8
PID    Username   Group      Machine
-----
Service   pid   machine   Connected at
-----
share     4600  192.8.1.242  Tue Apr 14 03:47:18 2009

Locked files:
Pid      Uid      DenyMode  Access   R/W      Oplock      SharePath Name  Time
-----
4600      99      DENY_NONE  0x100001  RDONLY   NONE        /share   .  Tue Apr 14 03:47:18
2009
```

testparm : ?????????????????? /etc/samba/smb.conf ???,Samba ??????? testparm ????? /etc/samba/smb.conf ??????,????????.

```
[root@benjr ~]# testparm /etc/samba/smb.conf
Load smb config files from /etc/samba/smb.conf
Processing section "[homes]"
Processing section "[printers]"
Loaded services file OK.
Press enter to see a dump of your service definitions
.....?
```

?????????? samba server ????

```
[root@benjr ~]# testparm /etc/samba/smb.conf 192.13.9.9
```

smbclient : ?? samba server ???????

```
[root@benjr ~]# smbclient -L benjr
Password:
```

```
Domain=[MYGROUP] OS=[Unix] Server=[Samba 3.0.28-0.el5.8]
  Sharename  Type  Comment
  -----  ----  -----
  share      Disk
  IPC$       IPC    IPC Service (Samba Server Version 3.0.28-0.el5.8)
Domain=[MYGROUP] OS=[Unix] Server=[Samba 3.0.28-0.el5.8]

  Server        Comment
  -----        -----
  BENJR        Samba Server Version 3.0.28-0.el5.8
  Workgroup    Master
  -----        -----
  MYGROUP
```

"mount or smbmount" :mount smaba ???? share ??

```
[root@unsvr root]# mount -t smbfs //benjr/share /mnt
Password:
[root@unsvr root]# smbmount //benjr/share /mnountpoint
Password:
```

RHEL5 - Samba (?) ???(iptables)

?? samba Server ?????24?????????,????????????????????????,????????????,????????? port ???,?????????.?
 iptables(firewall) ? SELinux ???? Samba ????????.????????????????? iptables(firewall) ? SELinux.?Linux??????
 iptables.?? RHEL5 ?? iptables ?????.?????:

```
[root@benjr ~]#system-config-securitylevel
```

????: ???????????????(iptables)?????????.

?????????? port ??,?????? port ??? SMB /NMB ??????????????.??**NetBIOS
(UDP ports 137 and 138, TCP ports 139) ? TCP port 445 for SMB file sharing without NetBIOS.**

????????? SSH ?????????? Text mode ????.

```
[root@benjr ~]#system-config-securitylevel-tui
```

??????????,?????????????.????????? /etc/sysconfig/iptables

```
[root@benjr ~]# cat /etc/sysconfig/iptables
# Firewall configuration written by system-config-securitylevel
# Manual customization of this file is not recommended.
*filter
:INPUT ACCEPT [0:0]
:FORWARD ACCEPT [0:0]
:OUTPUT ACCEPT [0:0]
:RH-Firewall-1-INPUT - [0:0]
-A INPUT -j RH-Firewall-1-INPUT
-A FORWARD -j RH-Firewall-1-INPUT
-A RH-Firewall-1-INPUT -i lo -j ACCEPT
-A RH-Firewall-1-INPUT -i ppp0 -j ACCEPT
-A RH-Firewall-1-INPUT -i eth0 -j ACCEPT
-A RH-Firewall-1-INPUT -p icmp --icmp-type any -j ACCEPT
-A RH-Firewall-1-INPUT -p 50 -j ACCEPT
-A RH-Firewall-1-INPUT -p 51 -j ACCEPT
-A RH-Firewall-1-INPUT -p udp --dport 5353 -d 224.0.0.251 -j ACCEPT
-A RH-Firewall-1-INPUT -p udp -m udp --dport 631 -j ACCEPT
-A RH-Firewall-1-INPUT -m state --state ESTABLISHED,RELATED -j ACCEPT
-A RH-Firewall-1-INPUT -m state --state NEW -m udp -p udp --dport 137 -j ACCEPT
-A RH-Firewall-1-INPUT -m state --state NEW -m udp -p udp --dport 138 -j ACCEPT
-A RH-Firewall-1-INPUT -m state --state NEW -m tcp -p tcp --dport 139 -j ACCEPT
-A RH-Firewall-1-INPUT -m state --state NEW -m tcp -p tcp --dport 445 -j ACCEPT
-A RH-Firewall-1-INPUT -j REJECT --reject-with icmp-host-prohibited
COMMIT
```

??:

?????? samba ????? port.

```
-A RH-Firewall-1-INPUT -m state --state NEW -m udp -p udp --dport 137 -j ACCEPT  
-A RH-Firewall-1-INPUT -m state --state NEW -m udp -p udp --dport 138 -j ACCEPT  
-A RH-Firewall-1-INPUT -m state --state NEW -m tcp -p tcp --dport 139 -j ACCEPT  
-A RH-Firewall-1-INPUT -m state --state NEW -m tcp -p tcp --dport 445 -j ACCEPT  
????????? iptables ,????????,????????? iptables .
```

```
[root@benjr ~]#chkconfig iptables on
```

????????????????????????? iptables ??.

```
[root@benjr ~]#service iptables start  
Starting httpd [OK]
```

???? iptables ??????

```
[root@benjr ~]#/sbin/service iptables save  
#????????? /etc/sysconfig/iptables
```

RHEL5 - Samba (?) ??????

?? RHEL5 ??? samba ??? 3.X,? samba 3.X ??????????????

????????????? samba server ?????? Windows ????

1.Share Level Security : ????????

security = share

2.User Level Security : ??? samba server ?????,???????????

security = user

3.Server Security : ???? Windows NT/2000/2003 ? samba server ?????

encrypt passwords = Yes

security = server

password server = "NetBIOS_name_of_a_DC"

4.Domain Security Mode : ????? Windows AD (Domain ? mixed mode)??? Windows NT 4 ??

workgroup = "name_of_NT_domain"

security = domain

5.ADS Security Mode : ????? Windows AD ??(Domain ? native mode)

realm = your.kerberos.REALM

security = ADS

ads server = your.kerberos.server

RHEL5 - Samba (?) Share ?????

???? Share Level Security : ????????,??????????????????.? X-windows ??? #system-config-samba ??

"Authentication Mode" ? Share.

?? #system-config-samba ??????,????????? samba ??? /etc/samba/smb.conf ,????????? share ????? samba ??
???????.

```
[root@benjr ~]# vi /etc/samba/smb.conf
[global]
  workgroup = MYGROUP
  netbios name = benjr
  security = share
```

1.????????????? security = share

2.netbios name ?????,?? Windows ?????,????? netbios name ? samba ???? hostname ?????.

?????? samb ?????????????????,????????? Linux ??????.??? Windows ?????.

????????????????? /share ????,????(#mkdir /share).????????????? (#chmod -R 777 /share),?????????
????,????????????? Linux ??????.??? #system-config-samba

?? Add Share ????????,?? samba ?????????????? Access ????? "Allow access to everyone".? Basic ????? Share name ??????????,?????????,?????????,????????????????? "writable" ??????(Guest User) ??????.?????????? ?? samba ??? /etc/samba/smb.conf ?????.

```
[root@benjr ~]# vi /etc/samba/smb.conf
=====
[share]
  comment = Temporary file space
  path = /tmp
  read only = no
  public = yes
```

[share] ?????? , path = /share ???? Linux ???,writable ??????????????.
Linux client ??????
I.smbclient ?? samba server ????????

```
[root@benjr ~]# smbclient -L benjr
Password:
Domain=[MYGROUP] OS=[Unix] Server=[Samba 3.0.28-0.el5.8]
```

```

Sharename   Type   Comment
-----
share       Disk
IPC$        IPC    IPC Service (Samba Server Version 3.0.28-0.el5.8)
Domain=[MYGROUP] OS=[Unix] Server=[Samba 3.0.28-0.el5.8]

Server      Comment
-----
BENJR       Samba Server Version 3.0.28-0.el5.8

Workgroup   Master
-----
MYGROUP

```

??? passwd ??????,?? enter ????

II."mount or smbmount" mount smaba ??? share ??

```

[root@unsvr root]# mount -t smbfs //benjr/share /mnt
Password:
[root@unsvr root]# smbmount //benjr/share /mnountpoint
Password:

```

??? passwd ??????,?? enter ????,?????????smaba ??????.

Windows client ????????

??????????,?? ??/?? ?? IP ??????(netbios name),????? samba server ??????,????????? samba server ??????
?.

RHEL5 - Samba (?) ?? samba User

? samba server security ? user ?????????? samba server ?????..????????????????????????????????? /etc/
samba/smbpasswd,RHEL5 ?????????????? passdb.tdb .

```

[root@benjr ~]# cat /etc/samba/smb.conf
# ----- Standalone Server Options -----
#
# Security can be set to user, share(deprecated) or server(deprecated)
#
# Backend to store user information in. New installations should
# use either tdbsam or ldapsam. smbpasswd is available for backwards
# compatibility. tdbsam requires no further configuration.
    security = user
    passdb backend = tdbsam

```

????????????????????????? Linux ???,?????????.????????? "Bob" ? "John"

```
[root@benjr ~]# adduser bob
```

```
[root@benjr ~]# adduser john
[root@benjr ~]# passwd bob
Changing password for user bob.
New UNIX password:
Retype new UNIX password:
passwd: all authentication tokens updated successfully.
[root@benjr ~]# passwd john
Changing password for user john.
New UNIX password:
Retype new UNIX password:
passwd: all authentication tokens updated successfully.
```

?????? system-config-samba ?????,?? #system-config-samba ?,?? Preferences / Samba Users ???? "Add User"

????????????? Linux User ??? Unix Username:?????? bob ? john.Windows Username ??? Unix Username ???.

???? #pdbedit -au ??????.

```
[root@benjr ~]# pdbedit -au bob
new password:
retype new password:
Unix username:    bob
NT username:
Account Flags:    [U      ]
User SID:         S-1-5-21-1634407166-380897321-584037179-1001
Primary Group SID: S-1-5-21-1634407166-380897321-584037179-513
Full Name:
Home Directory:   \\benjr\bob
HomeDir Drive:
Logon Script:
Profile Path:     \\benjr\bob\profile
Domain:          BENJR
Account desc:
Workstations:
Munged dial:
Logon time:       0
Logoff time:      never
Kickoff time:     never
Password last set: Fri, 17 Apr 2009 03:38:39 CST
Password can change: Fri, 17 Apr 2009 03:38:39 CST
Password must change: never
```

```
Last bad password : 0
Bad password count : 0
Logon hours      : FFFFFFFFFFFFFFFFFFFFFFFFFFFFFFF
[root@benjr ~]# pdredit -au john
new password:
retype new password:
Unix username:    john
NT username:
Account Flags:    [U      ]
User SID:          S-1-5-21-1634407166-380897321-584037179-1002
Primary Group SID: S-1-5-21-1634407166-380897321-584037179-513
Full Name:
Home Directory:   \\benjr\john
HomeDir Drive:
Logon Script:
Profile Path:     \\benjr\john\profile
Domain:           BENJR
Account desc:
Workstations:
Munged dial:
Logon time:       0
Logoff time:      never
Kickoff time:     never
Password last set: Fri, 17 Apr 2009 03:38:51 CST
Password can change: Fri, 17 Apr 2009 03:38:51 CST
Password must change: never
Last bad password : 0
Bad password count : 0
Logon hours      : FFFFFFFFFFFFFFFFFFFFFFFFFFFFFFF
```

#pdredit ???? -L ?????????? samba ????.

```
[root@benjr ~]# pdredit -L
john:501:
bob:500:
```

note:

?????? RedHat ???????????????,?????? system-config-samba ???????,??!!?????????.?????????????????(An account for this user already exists. Please try again).

?!!!!????????!!????????? #pdbeedit -L ??????????,??????,??? system-config-samba ??? /etc/samba/smbpasswd ?
?????????,???? RHEL5 ?????????????????? passdb.tdb ,?????? RHEL5.2 ??????,??? RHEL5.3 ????.???? RHEL5.2 ??
????????? system-config-samba-1.2.40 ??????,????????.

https://bugzilla.redhat.com/show_bug.cgi?id=236557

RHEL5 - Samba (?) ???

????????????????????????????,?????? Linux ????.

1.? Bob ?? Samba Server ??????????,?????????????.? Share Level Security ???????????????????,? Bob ???
Samba Server ??????(????????? Windows ? LDAP ???,??????).

2.? Bob ???????????,??? Samba Server ??????????????????.

3.?? Samba ? Bob ???????????,?? Linux ?????????????????? Linux ???????.

Linux ?????????????,????????????????????????,?????? .

#ls -l (ls "list directory contents",-l "use a long listing format")????????????????.

??????????[??][??][????]

? -rw-r--r-- [??]????????????????,??????,????? rwx ,??????????????????.

??? User ???????????????,????????[??].

??? Group????????????????,????????[?????].

??? Other ??[?????]??????.

????????? rwx ,?????? rwx ????????????????

I. ?????:

??(r):??cat????

??(w):??cp,move?????

???(x):??????

II. ?????:

??(r):??????????????,?????x???.?? ls ???????.

??(w): ?????????????????,?????x???.??cp,move,touch??????.

note: ????? w ?????????????? w ???,??????????????.

???(x): ?? cd (change directory)???????

note:????User,group?????,???? User ?.

???????:

```
[root@benjr ~]# mkdir /share
[root@benjr ~]# ll -d /share
drwxr-xr-x 2 root root 4096 Apr 20 08:31 /share
```

????????????????? rx ????????.????? Bob ??? /share ??????.

1.other ??? w (?) ???.

2.? /share ? user ?? Bob.

3.????(Group),?????????.??? w (?) ???.

????????????????????? 777.