

????
?????

```
cd /etc/yum.repos.d/  
wget http://download.openvz.org/openvz.repo
```

?? openvz.repo?

```
[openvz-utils]  
name=OpenVZ utilities  
#baseurl=http://download.openvz.org/current/  
mirrorlist=http://download.openvz.org/mirrors-current  
enabled=1  
gpgcheck=1  
gpgkey=http://download.openvz.org/RPM-GPG-Key-OpenVZ
```

```
[openvz-kernel-rhel5]  
name=OpenVZ RHEL5-based kernel  
#baseurl=http://download.openvz.org/kernel/branches/rhel5-2.6.18/current/  
mirrorlist=http://download.openvz.org/kernel/mirrors-rhel5-2.6.18  
enabled=1  
gpgcheck=1  
gpgkey=http://download.openvz.org/RPM-GPG-Key-OpenVZ
```

???

?? rhel5 ?????????????????? enabled=0?

?????????

```
rpm --import http://download.openvz.org/RPM-GPG-Key-OpenVZ
```

?? OpenVZ ??

```
yum install ovzkernel.i686
```

???

?? CentOS 6.x ?????????? vkernel.[ARCH], ARCH ??? i386, i686 ? 64-bit ? x86_64?

?????????????????

1. ?? /boot/grub/grub.conf????????? kernel?????
2. ?? /etc/sysctl.conf?

3. ?? SELINUX?

/boot/grub/grub.conf?

```
title OpenVZ (2.6.18-274.3.1.el5.028stab094.3)
```

```
  root (hd0,0)
```

```
  kernel /vmlinuz-2.6.18-274.3.1.el5.028stab094.3 ro root=/dev/VolGroup00/LogVol00 selinux=0
```

```
  initrd /initrd-2.6.18-274.3.1.el5.028stab094.3.img
```

/etc/sysctl.conf?

??????????????

for OpenVZ

```
net.ipv4.ip_forward = 1
```

```
net.ipv4.conf.default.proxy_arp = 0
```

```
net.ipv4.conf.all.rp_filter = 1
```

```
kernel.sysrq = 1
```

```
net.ipv4.conf.default.send_redirects = 1
```

```
net.ipv4.conf.all.send_redirects = 0
```

/etc/selinux/config?

```
SELINUX=disabled
```

??????????????

?? vzctl ??

```
yum install vzctl vzquota
```

?? OpenVZ ??

```
service vz start
```

?????????????????????????????????????? [?? WebVZ?](#)

????

- http://wiki.openvz.org/Quick_installation
- <http://wiki.centos.org/zh-tw/HowTos/...ization/OpenVZ>