

2. ????????????????

```
#> lsof | grep 253,2 ;?????????????
```

```
[root@gtnas02 ~]# lsof | grep 253,2
```

```
smbd  11934  root 19r  DIR  253,2  4096  9112573 /TD2/rene/Realtek
```

```
// ????????????
```

```
#> kill 11934
```

3. ??? LV ????

```
[root@gtnas02 ~]# lvdisplay vg1/td2_winLV
```

```
--- Logical volume ---
```

```
LV Name      /dev/vg1/td2_winLV
```

```
VG Name      vg1
```

```
LV UUID      U2Zcy0-AW0q-4Esf-7kpM-ny3U-bee3-S4HRDg
```

```
LV Write Access  read/write
```

```
LV Status     available
```

```
# open       0
```

```
LV Size       200.00 GB
```

```
Current LE    51200
```

```
Segments      3
```

```
Allocation    inherit
```

```
Read ahead sectors  0
```

```
Block device   253:2
```

```
open ??? 0 ??? LV ????????
```

4. ?? LV ????????

```
[root@gtnas02 ~]# lvchange -an vg1/td2_winLV
```

```
[root@gtnas02 ~]# lvdisplay vg1/td2_winLV
```

```
--- Logical volume ---
```

```
LV Name      /dev/vg1/td2_winLV
```

```
VG Name      vg1
```

```
LV UUID      U2Zcy0-AW0q-4Esf-7kpM-ny3U-bee3-S4HRDg
```

```
LV Write Access  read/write
```

```
LV Status     NOT available
```

```
LV Size       200.00 GB
```

```
Current LE    51200
```

```
Segments      3
```

```
Allocation    inherit
```

```
Read ahead sectors  0
```

```
// ??????????????
```

```
[root@gtnas02 ~]# lvdisplay -C
```

```
LV    VG    Attr  LSize  Origin Snap%  Move Log Copy%
```

```
autoftpLV SAN01 -wi-ao 400.00G
sourceLV  SAN01 -wi-ao 100.00G
stdfLV   SAN01 -wi-ao  5.00G
td2_winLV vg1  -wi--- 200.00G
testLV   vg1  -wi-ao 50.00G
worktmpLV vg1  -wi-ao  5.00G
```

???